Chapter 1

The `minitoc` package

Contents

1.1 Introduction **1**
1.2 Usage **2**
1.2.1 Fonts and Titles 6
1.2.2 Special Features 8
Horizontal Rules 8
Page Numbers 9
The "Chapter 0" Problem 9
1.2.3 Usage with MS-DOS 9
1.3 The `minitocoff` package **10**

Tables

1.1 Commands for a `minitoc` 3
1.2 Commands for a `secttoc` 4
1.3 Commands for a `parttoc` 5

1.1 Introduction

This package, initially written by Nigel Ward and Dan Jurafsky, has been almost completely redesigned at CERT/ONERA by Jean-Pierre Drucbert.

It creates a mini-table of contents (a "minitoc" [1]) at the beginning of each chapter of the document. It is also possible to have a mini-list of figures (a "minilof") and a mini-list of tables (a "minilot"). The document class should of course define chapters (styles like `book` or `report`) or sections (styles like `article`). Thus, this package should not be used with document classes without sectioning commands (like `letter`). When the document class defines a "part" sectionning level (i.e. classes like `book`, `report` and `article`), you can create a "partial" table of contents (a "parttoc") at the beginning of each part of the document. It is also possible to have a partial list of figures (a "partlof") and a partial list of tables (a "partlot"). When the document class has no `\chapter` command but has a `\section` command, you may use section level tables of contents ("secttoc") at the beginning of each section.

Note: you cannot use chapter level and section level table of contents in the same document. This restriction is intented to avoid documents full of local tables of contents, list of figures and tables at every sectionning level.

The current version of this package is #24.

Note: the commands relative to the part level are defined only if the document class defines `\part`. The commands relative to the section level are defined only if the document class does not define `\chapter`.

1.2 Usage

To use the `minitoc` package, you must introduce a command

```
\usepackage{minitoc}
```

in the preamble of your document. The mini-table of contents will appear in the chapter, after the `\chapter` command, at the point of the `\minitoc` command. The `\minitoc` command may occur *anywhere* inside a chapter. Of course, it is better to put it at the beginning of the chapter, eventually after some introductory material. But you can also decide to put it at the end of the chapter. You should use the same conventions in all chapters. If you want to add the mini-table of contents for a chapter, you must use the sequence given in Table 1.1 For each mini-table of contents, an auxiliary file

[1] The `minitoc` package introduces its own jargon, explained in this note. It should not be too difficult, however, to learn and use.

```
\documentclass[...]{book}
\usepackage{minitoc}
...
\setcounter{minitocdepth}{2}          default
\setlength{\mtcindent}{24pt}          default
\renewcommand{\mtcfont}{\small\rm}    default
\renewcommand{\mtcSfont}{\small\bf}   default
...
\begin{document}
...
\dominitoc
\dominilof
\dominilot
\tableofcontents                      or \faketableofcontents
\listoffigures                        or \fakelistoffigures
\listoftables                         or \fakelistoftables
...
\chapter{...}
\minitoc                              if you want one
\minilof                              if you want one
\minilot                              if you want one
...
```

Table 1.1: Commands for a minitoc

will be created with a name of the form ⟨*document*⟩.`mtc`⟨N⟩, where ⟨N⟩ is the absolute chapter number. "Absolute" means that this number is unique, and increasing from the first chapter. The suffix is .`mlf`⟨N⟩ for mini-lists of figures and is .`mlt`⟨N⟩ for mini-lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3).

The section-level table of contents will appear in the section, after the `\section` command, at the point of the `secttoc` command. The `\secttoc` command may occur *anywhere* inside a section. Of course, it is better to put it at the beginning of the section, eventually after some introductory material. You should use the same conventions in all sections. If you want to add the section-level table of contents for a section, you must use the sequence given in Table 1.2 For each section-level table of contents, an auxiliary file will be created with a name of the form ⟨*document*⟩.`stc`⟨N⟩, where ⟨N⟩ is the absolute section number. The suffix is .`slf`⟨N⟩ for section-level lists

```
\documentclass[...]{article}
\usepackage{minitoc}
...
\setcounter{\secttocdepth}{2}          default
\setlength{\stcindent}{24pt}           default
\renewcommand{\stcfont}{\small\rm}     default
\renewcommand{\stcSSfont}{\small\bf}   default
...
\begin{document}
...
\dosecttoc
\dosectlof
\dosectlot
\tableofcontents                       or \faketableofcontents
\listoffigures                         or \fakelistoffigures
\listoftables                          or \fakelistoftables
...
\chapter{...}
\secttoc                               if you want one
\sectlof                               if you want one
\sectlot                               if you want one
...
```

Table 1.2: Commands for a secttoc

of figures and is .slt⟨N⟩ for section-level lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3).

If you want to add the partial table of contents for a part, you must use the sequence given in Table 1.3. For each partial table of contents, an auxiliary file will be created with a name of the form ⟨*document*⟩.ptc⟨N⟩, where ⟨N⟩ is the part number. The suffix is .plf⟨N⟩ for partial lists of figures and is .plt⟨N⟩ for partial lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3).

Note: the user is responsible of requiring or not requiring a mini-toc (lof or lot) for some chapter. Asking a minilof for a chapter without any figure will result in an empty and ugly mini list of figures (i.e. the title and two horizontal rules). He is also responsible of requiring or not requiring a partial

```
\documentclass[...]{book}
\usepackage{minitoc}
...
\setcounter{parttocdepth}{2}                default
\setlength{\ptcindent}{0pt}                 default
\renewcommand{\ptcfont}{\normalsize\rm}     default
\renewcommand{\ptcCfont}{\normalsize\bf}    default
\renewcommand{\ptcSfont}{\normalsize\rm}    default
...
\begin{document}
...
\doparttoc
\dopartlof
\dopartlot
\tableofcontents                            or \faketableofcontents
\listoffigures                              or \fakelistoffigures
\listoftables                               or \fakelistoftables
...
\part{...}
\parttoc                                    if you want one
\partlof                                    if you want one
\partlot                                    if you want one
...
```

Table 1.3: Commands for a parttoc

toc (lof or lot) for some part. Asking a partlof for a part without any figure will result in an empty and ugly part list of figures (i.e. the title alone on a page). Analogous remarks apply to section-level tables of contents (secttoc, sectlof and sectlot).

By default, the mini-tables and partial tables of contents contain only references to sections and subsections. The `minitocdepth` and `parttocdepth` counters, similar to `tocdepth`, allows the user to modify this behaviour. Mini or partial lists of figures or tables are not affected by the value of these counters.

Note: if you are using `\chapter*` and a

```
\addcontentsline{toc}{chapter}{...}
```

command to add something in the table of contents, the numbering of minitoc files would be altered. To avoid that problem, say

```
\addcontentsline{toc}{starchapter}{...}
```

You *should not* use `\minitoc` in a `\chapter*`. Similar remarks apply to the part and section level.

1.2.1 Fonts and Titles

The mini and partial tables and lists are typeset in a `verse`-like environment, and can be split over pages. The mini-table of contents is typeset in the `\mtcfont` font, which is `\small\rm` by default. Section entries are typeset in the `\mtcSfont` font, which is `\small\bf` by default. For subsections, subsubsections, paragraphs and subparagraphs, the commands `\mtcSSfont`, `\mtcSSSfont`, `\mtcPfont` and `\mtcSPfont` are available (by default, `\small\rm`) to enable the use of various fonts. Mini lists of figures and tables are typeset in the fonts `\mlffont` and `\mltfont`, which are `\small\rm` by default.

Titles are typeset in the `\mtifont` (`\large\bf` by default) font and the texts of the titles are defined by `\mtctitle`, `\mlftitle` and `\mlttitle`, which are the strings "Contents", "Figures" and "Tables" by default. These commands should be redefined by `\renewcommand` for languages other than english. The option files `mtcfrench.sty` and `mtcenglish.sty` (and others [2]) are available. You can easily prepare a similar style for your preferred language.

The partial table of contents is typeset in the `\ptcfont` font, which is defined as `\normalsize\rm` by default. Chapter entries are typeset in the `\ptcCfont` font, which is `\normalsize\bf` by default. Section entries are typeset in the `\ptcSfont` font, which is `\normalsize\rm` by default. For subsections, subsubsections, paragraphs and subparagraphs, the commands `\ptcSSfont`, `\ptcSSSfont`, `\ptcPfont` and `\ptcSPfont` are available (by

[2] The strings defined in these option files were taken from the **Babel** system of Johannes Braams and some were adapted. Other languages are welcome.

default, \normalsize\rm) if you want to use various fonts. Partial lists of figures and tables are typeset in the fonts \mlffont and \mltfont, which are \normalsize\rm by default.

Titles are typeset in the \ptifont (\Huge\bf by default) font and the texts of the titles are defined by \ptctitle, \plftitle and \plttitle, which are the strings "Table of Contents", "List of Figures" and "List of Tables" by default. These commands should be redefined by \renewcommand for languages other than english. The option files mtcfrench.sty and mtcenglish.sty (and others, see footnote 2 above) are available. You can easily prepare a similar style for your preferred language.

The section-level table of contents is typeset in the \stcfont font, which is defined as \normalsize\rm by default. Subsection entries are typeset in the \stcSSfont font, which is \normalsize\bf by default. Subsubsection entries are typeset in the \stcSSSfont font, which is \normalsize\rm by default. For subsubsections, paragraphs and subparagraphs, the commands \stcSSSfont, \stcPfont and \stcSPfont are available (by default, \normalsize\rm) if you want to use various fonts. Partial lists of figures and tables are typeset in the fonts \slffont and \sltfont, which are \normalsize\rm by default.

Titles are typeset in the \stifont (\normalsize\bf by default) font and the texts of the titles are defined by \stctitle, \slftitle and \slttitle, which are the strings "Contents", "Figures" and "Tables" by default. These commands should be redefined by \renewcommand for languages other than english. The option files mtcfrench.sty and mtcenglish.sty (and others, see footnote 2 above) are available. You can easily prepare a similar style for your preferred language.

By default, titles are on the left. The commands \dominitoc, \dominilof and \dominilot accept an optional argument to change the default position of the corresponding title: [l] for left (default), [c] for center, [r] for right, or [e] (or [n]) for empty (no title). The change is global for all the document.

If you want to change the position of the title for only one minitoc (or minilof or minilof), just use such an optional argument with the command \minitoc (or \minilof or \minilot).

By default, titles are on the left. The commands \doparttoc, \dopartlof and \dopartlot accept an optional argument to change the default position

of the corresponding title: [l] for left (default), [c] for center, [r] for right, or [e] (or [n])for empty (no title). The change is global for all the document.

By default, titles are on the left. The commands \dosecttoc, \dosectlof and \dosectlot accept an optional argument to change the default position of the corresponding title: [l] for left (default), [c] for center, [r] for right, or [e] (or [n]) for empty (no title). The change is global for all the document.

If you want to change the position of the title for only one secttoc (or sectlof or sectlof), just use such an optional argument with the command \secttoc (or \sectlof or \sectlot).

The mini-tables and lists, as partial and section-level tables and lists, are using some space on the first pages on each chapter, part or section, thus the page numbers are altered. After the first LaTeX run, the mini-tables and lists, partial tables and lists and section-level tables and lists will be empty; after the second run, they appear, but because they modify the page numbering, page numbers are wrong; after the third LaTeX run, the mini, partial and section-level tables and lists should be correct.

1.2.2 Special Features

Horizontal Rules

By default, most of minitocs and siblings have horizontal rules after their titles and at their ends. The exception is the "partoc" in a book- or report-like document (i.e. when \chapter is defined). To activate or desactivate these rules, the following commands are available:

				defaults for		
	rules in		no rules in	book	report	article
\ptcrule	parttocs	\noptcrule	parttocs	**N**	**N**	**Y**
\mtcrule	minitocs	\nomtcrule	minitocs	**Y**	**Y**	**N-A**
\stcrule	secttocs	\nostcrule	secttocs	**N-A**	**N-A**	**Y**

Page Numbers

By default, the page numbers are listed in each minitoc, minilof, etc. Some authors want only the section titles (with the section numbers), but not the page numbers. Hence the obvious declarations below are available:

Type	Page numbers (Default)	No page numbers
minitoc	`\mtcpagenumbers`	`\nomtcpagenumbers`
secttoc	`\stcpagenumbers`	`\nostcpagenumbers`
parttoc	`\ptcpagenumbers`	`\noptcpagenumbers`
minilof	`\mlfpagenumbers`	`\nomlfpagenumbers`
sectlof	`\slfpagenumbers`	`\noslfpagenumbers`
partlof	`\plfpagenumbers`	`\noplfpagenumbers`
minilot	`\mltpagenumbers`	`\nomltpagenumbers`
sectlot	`\sltpagenumbers`	`\nosltpagenumbers`
partlot	`\pltpagenumbers`	`\nopltpagenumbers`

The "Chapter 0" Problem

Some documents do not begin with chapter number one, but with chapter number zero (or even a weirder number). To make the `minitoc` option work with such documents, you must insert the command

`\firstchapteris{`$\langle N \rangle$`}`

before the `\dominitoc` and analogous commands. $\langle N \rangle$ is the number of your first chapter. This command *does not* modify the numbering of chapters, you must use a `\addtocounter{chapter}{-1}` command to get a first chapter numbered 0. The `\firstpartis` and `\firstsectionis` commands are analogous for parts and sections with a non standard numbering.

Since version #17c, these commands are obsolete, as this problem has been solved. Thus they just give a harmless warning.

1.2.3 Usage with MS-DOS

Under MS-DOS (and other PC oriented operating systems), the filename

extensions are limited to 3 characters. Thus, it is olnl necessary to edit very slightly the file `minitoc.sty`. You have just to uncomment the line where `\SHORTEXT` is defined. All other modifications will be done automatically. The `.mtc`$\langle N\rangle$ suffix will become `.M`$\langle N\rangle$, where $\langle N\rangle$ is the absolute chapter number. The suffixes `.mlf`$\langle N\rangle$ and `.mlt`$\langle N\rangle$ become `.F`$\langle N\rangle$ and `.T`$\langle N\rangle$. The `.ptc`$\langle N\rangle$ suffix will become `.P`$\langle N\rangle$, where $\langle N\rangle$ is the part number. The suffixes `.plf`$\langle N\rangle$ and `.plt`$\langle N\rangle$ become `.G`$\langle N\rangle$ and `.U`$\langle N\rangle$. The `.stc`$\langle N\rangle$ suffix will become `.S`$\langle N\rangle$, where $\langle N\rangle$ is the absolute section number. The suffixes `.slf`$\langle N\rangle$ and `.slt`$\langle N\rangle$ become `.H`$\langle N\rangle$ and `.V`$\langle N\rangle$. Of course, this implies a limit of 99 chapters in a document, but do you really need so many chapters (or sections in an article)? The limit of 99 parts does not seem too serious.

1.3 The `minitocoff` package

When a document has been prepared with the `minitoc` package, it contains many `minitoc` specific commands, most of them being `\faketableofcontents` and `\minitoc` commands (and their equivalents for lists of figures and tables). If you want to typeset this document without any mini-table, you have just to replace the `minitoc` package by the `minitocoff` package, and all these commands will be ignored. At least two LaTeX runs will be necessary to get a correct page numbering and correct cross references.

Chapter 2

Frequently Asked Questions

Here is a list of problems and frequently asked questions about `minitoc.sty`. If your version has a number less than 24, please upgrade to version #24.

1. How avoid a page break near the rules before and after the minitoc?
   This problem seemed solved since version #8, but version #12 adds better fixes.

2. How about implementing others layouts for the minitoc? Suggestions are welcome.

3. `\\` in a contents line makes an error.
   Use `\protect\linebreak`.

4. If you reorder chapters, havoc follows... minitocs going in wrong chapters.
   The best way seems to make one run with the `minitocoff` *package replacing the* `minitoc` *package, then restore the* `minitoc` *package and re-execute LaTeX three times (yes, it is time consuming...). Running with the* `minitocoff` *package ensures that auxiliary are cleared from "spurious" commands introduced by* `minitoc`.

5. This option creates auxiliary files with extensions like .`mtc`$\langle N \rangle$. Some operating systems allow only 3 letters extensions. What to do?
   If you have an operating system which tolerates only short file name extensions (of 3 characters, like with MS-DOS), you must edit the file `minitoc.sty`*: find the line containing "*`%\def\SHORTEXT`*" and remove*

the leading percent sign. No other modification is needed: all is automatic!

6. Do not cheat with the "`chapter`" counter, i.e. do not write horrible things like `\setcounter{chapter}{6}`. The mechanism would break. It is better to add `\chapter` commands, to create empty (but numbered in a legal way) chapters. Since version #10, `minitoc.sty` works with appendices. Version #19 allows to begin with a chapter other that number 1.

7. Some demanding users want to have minilof, minilot and minibbl. First, minibbl is an other problem, strongly related to the BIBTEX's dealing with `.aux` files. Look at `chapterbib.sty`. Version #13 has implemented basic minilofs and minilots. Minibbls are not the aim of this package.

8. This package creates a lot of auxiliary files and some users argue that it is too many. A deep redesign would be necessary to avoid that. Using only one big auxiliary file (or one for all minitocs, one for all minilofs, ...) would make the reading of such file very slow, and it would be read for each `\miniXXX` macro!

9. How to do minitocs (minilofs and minilots) at levels other than chapter? Here also, some redesign is needed. From version #15, there are parttocs, partlofs and partlots for the part level in book-like and article-like documents, secttocs, sectlofs and sectlots for the section level in article-like documents. Note that you can not have minitocs features at chapter and section level in the same document, because doing so would make an unreadable monster. The user must choose the main style of the document accordingly to the size of it (e.g. do not write an article of more than 130 sections: this is a report, or even a book!).

	part	**chapter**	**section**
`book`	*	*	
`report`	*	*	
`article`	*		*

10. Since version #23, works with document classes resetting chapter (or section) number at each part.