# The $pdfT_{EX} 0.12 + user manual$

Sebastian Rahtz

Hàn Thế Thành thanh@informatics.muni.cz s.rahtz@elsevier.co.uk

April 1998

# 1 Introduction

The main purpose of the pdfTEX project was to create an extension of TEX that could create PDF directly from TEX source files and improve/enhance the result of TEX typesetting with the help of PDF. pdfTEX contains TEX as a subset. When PDF output is not selected, pdfTEX produces normal DVI output, otherwise it produces PDF output that looks identical to the DVI output. The next stage of the project, apart from fixing any errors in the program, is to investigate alternative justification algorithms, possibly making use of multiple master fonts.

 $pdfT_EX$  is based on the original  $T_EX$  sources and web2c, and has been successfully compiled on Unix, Amiga, Win32 and DOS systems. It is still under beta development and all features are liable to change.

This manual was compiled by Sebastian Rahtz from notes and examples by Hàn Thế Thành. Many thanks are due to members of the pdfT<sub>E</sub>X mailing list (most notably Hans Hagen), whose questions and answers have contributed much to this manual.

# 2 Getting started

This section describes steps needed to get  $pdfT_EX$  run on a system where  $pdfT_EX$  is not installed. Some  $T_EX$  packages have already contained  $pdfT_EX$  as a part, such as MikTeX, Web2c for Win32 or teTeX, where we need not to bother with  $pdfT_EX$  installation. Note that installation descriptions in this manual are web2c-specific.

# 2.1 Getting sources and binaries

Latest sources of  $pdfT_EX$  are distributed together with precompiled binaries of  $pdfT_EX$  for some platforms, including Linux, SGI IRIX, Sun SPARC Solaris

and DOS (DJGPP). The primary location is ftp://ftp.cstug.cz/pub/tex/local/cstug/thanh/pdftex-testing/latest

For Win32 systems (Windows 95, Windows NT) there are two packages that contain pdfT<sub>E</sub>X, both in CTAN:systems/win32. Web2c for Win32 is maintained by Fabrice Popineau (mailto:popineau@ese-metz.fr), and MikTeX by Christian Schenk (mailto:cschenk@berlin.snafu.de).

A binary version of pdfTEX for Amiga is made available (CTAN:systems/pdftex/bin/Amiga) by Andreas Scherer (mailto:scherer@physik.rwth-aachen.de).

# 2.2 Compiling

If there is no precompiled binary of  $pdfT_EX$  for our system, we need to build  $pdfT_EX$  from sources. The compilation is expected to be easy on UNIX-like systems and can be described best by example. Assuming that all needed files are downloaded to HOME/pdftex, the following steps are needed to compile  $pdfT_EX$  (based on web2c-7.2) on a UNIX system :

```
cd $HOME/pdftex
gunzip < web-7.2.tar.gz | tar xvf -
gunzip < web2c-7.2.tar.gz | tar xvf -
gunzip < pdftex.tar.gz | tar xvf -
mv pdftexdir web2c-7.2/web2c
cd web2c-7.2
./configure
cd ./web2c
make pdftex
```

Apart from the binary of pdfT<sub>E</sub>X the compilation also produces several other files which are needed for running  $pdfT_{E}X$ :

- pdftex.pool so-called pool file, needed for creating formats, located in web2c-7.2/web2c
- texmf.cnf-web2crun-time configuration file, located in web2c-7.2/kpathsea
- ttf2afm an external program to generate AFM file from TrueType fonts, located in web2c-7.2/web2c/pdftexdir

For precompiled binaries these files are included in the zip archive containing the binary (pdftex.zip).

# 2.3 Getting pdfT<sub>F</sub>X-specific platform-independent files

Apart from above-mentioned files, there is another zip archive (pdftexlib-0.12.zip) in pdfT<sub>E</sub>X distribution which contains platform-independent files required for running pdftex: pdftex config file (pdftex.cfg), encoding vectors (\*.enc), map files (\*.map), macros (\*.tex). Unpacking this archive (don't forget -d option when using pkunzip) will create a texmf tree containing pdfT<sub>E</sub>X-specific files.

# 2.4 Placing files

The next step is to place the binaries somewhere in PATH. We also need to make a copy (or symbolic link) of pdftex and name it as pdflatex if we want to use IATEX. texmf.cnf, pdftex.pool and directory texmf/ (created by unpacking pdftexlib-0.12.zip) should be also moved to "appropriate" place (see below).

#### 2.5 Setting search paths

web2c-based programs, including pdfT<sub>E</sub>X, use a web2c run-time configuration file called texmf.cnf. This file can be found via the user-set environment variable TEXMFCNF or via the compile-time default value if the former is not set. It is strongly recommended to use the first way. Then we need to edit texmf.cnf so pdfT<sub>E</sub>X can find all necessary files. Usually one has to edit TEXMFS and maybe some next. When runing pdfT<sub>E</sub>X, some extra search paths are used beyond those normally requested by T<sub>E</sub>X itself:

- VFFONTS the path where pdfT<sub>F</sub>X looks for virtual fonts.
- T1FONTS the path where  $pdfT_FX$  looks for Type1 fonts.
- TTFONTS the path where pdfT<sub>F</sub>X looks for TrueType fonts.
- PKFONTS the path where  $pdfT_EX$  looks for PK fonts.
- TEXPSHEADERS the path where pdfTEX looks for the configuration file pdftex.cfg, font mapping files (\*.map), encoding files (\*.enc), and PNG pictures.

# 2.6 The pdfT<sub>E</sub>X configuration file

When pdfT<sub>E</sub>X starts, apart from web2c configuration file it reads a  $pdfT_{E}X$  configuration file called pdftex.cfg, searched for in the TEXPSHEADERS path. As web2c systems commonly specify a 'private' tree for pdfT<sub>E</sub>X where configuration and map files are located, this allows individual users or projects to maintain customized versions of the configuration file, and means that specific T<sub>E</sub>X input files need not set any pdfT<sub>E</sub>X-specific macros.

The configuration file is used to set default values for the following parameters (all of which can be over-ridden in the  $T_{FX}$  source file):

- **output\_format** Integer parameter specifying whether the output format should be DVI or PDF. Positive value means PDF output, otherwise DVI output.
- compress\_level Integer parameter specifying the level of text compression via zlib. Zero means no compression, 1 means fastest, 9 means best, 2..8 means something in between.
- decimal\_digits The number of decimal digits after the decimal point.

- page\_width, page\_height Dimension parameters specifying the page width and page height of PDF output. If not specified then page width is calculated as width of the box being shiped out  $+ 2 \times (1in + \belowfset)$ . The page height is similar.
- horigin, vorigin Dimension parameters specifying the offset of the  $T_EX$  output box from the top left corner of the 'paper'
- map The name of the font mapping file (similar to those used by many DVI to PostScript drivers); more than one map file can be specified, using multiple map lines. If the name of the map file is prefixed with a +, its values are appended to the existing set, otherwise they replace it.

A typical pdftex.cfg file looks like this, setting up output for A4 paper size and the standard  $T_{EX}$  offset of 1 inch, and loading two map files for fonts:

```
output_format 1
compress_level 0
decimal_digits 2
page_width 210mm
page_height 297mm
horigin 1in
vorigin 1in
map standard.map
map +cm.map
```

# 2.7 Creating formats

Formats for pdfT<sub>E</sub>X are created in the same way as for T<sub>E</sub>X. For plain T<sub>E</sub>X and  $I_{F}X$  it looks like:

```
pdftex -ini -fmt=pdftex plain \\dump
pdftex -ini -fmt=pdflatex latex.ltx
```

The formats (pdftex, pdflatex or other formats) should be placed in the TEXFORMATS path.

# 2.8 Testing the installation

Now we can test the installation:

#### pdftex example

If the installation is ok, this run should produce a file called example.pdf. The file example.tex is also a good place to look how pdfT<sub>E</sub>X new primitives are used.

## 2.9 Common problems

The most common problem with installation is  $pdfT_EX$  complains that something cannot be found. In such case the best place to look/edit is the file texmf.cnf. Also setting KPATHSEA\_DEBUG=255 before running

pdftex or running pdfT<sub>E</sub>X with option -k 255 will cause pdfT<sub>E</sub>X writes a lot of debugging information, which may be useful to find out the troubles. Variables in texmf.cnf can be overwritten by environment variables. Here are some most common problems with getting started:

"! I can't read tex.pool; bad path?"

Probably TEXMFCNF is not set correctly, or TEXPOOL (in texmf.cnf) doesn't contain path to pool file (pdftex.pool).

"! You have to increase POOLSIZE."

Value of pool\_size in texmf.cnf must be increased. If pool\_size is not specified in texmf.cnf then we can add something like

"pool\_size = 500000"
"I can't find the format file 'pdftex.fmt'!"
or
"I can't find the format file 'pdflatex.fmt'!"

Format is not created (see above how to do that) or is not properly placed. Make sure that TEXFORMATS in texmf.cnf contains path to pdftex.fmt or pdflatex.fmt.

pdfT<sub>E</sub>X cannot find: config file (pdftex.cfg), map files (\*.map), encoding vectors (\*.enc), virtual fonts, Type1 fonts, TrueType fonts or image files.

Make sure that the required file exists and the correspoding variable in texmf.cnf contains path to the file. See above which variables  $pdfT_EX$  needs apart from the ones TeX uses.

# 3 Fonts

pdfT<sub>E</sub>X can work with Type 1 and TrueType fonts at present, and a source must be available for all fonts used in the document, except for the 14 base fonts supplied by Acrobat Reader (Times, Helvetica, Courier, Symbol and Dingbats). It is possible to use METAFONT-generated fonts in pdfT<sub>E</sub>X—however it is strongly recommended not to use METAFONT-fonts if an equivalent is available in Type 1 or TrueType format, as the resulting Type 3 fonts render very poorly in Acrobat Reader. Given the free availability of Type 1 versions of all the Computer Modern fonts, and the ability to use standard PostScript fonts without further ado, most existing T<sub>E</sub>X users should be able to experiment with pdfT<sub>E</sub>X.

# 3.1 Map files

pdfT<sub>E</sub>X reads map files (specified in the configuration file (see above, section 2.6), in which reencoding and partial downloading for each font are specified. Every font needed must be listed, each on a separate line. The syntax of each line is similiar to dvips' map files (but may be changed later), and can contain up to the following (some are optional) fields in fixed order: texname, basename, fontflags, fontfile and encodingfile.

texname: the name of the TFM file

basename: the base font name (PostScript font name)

- *fontflags*: the flags specifying some chracteristics of the font. If not specified then will be treated as 4.
- fontfile: the name of the font source file. This must be a Type 1 or TrueType font file. If it is preceded by a < then the font file will be partly downloaded; if it preceded by a double << then the font file will be included entirely. If it is preceded by a !, the font is not read at all, and is assumed to be available on the users Acrobat platform. Note that the standard 14 fonts are never downloaded, even they are specified to be downloaded in some map file.</p>
- *encoding*: a file containing the encoding vector to be used for the font. The file name may be preceded by a <, but the effect is the same. The format of the encoding vector is identical to that used by dvips.

If no encoding is specified, the font's built-in default encoding is used. Here are some sample lines:

Include font entirely without reencoding:

pgsr8r GillSans <<pgsr8a.pfb

Include font partly without reencoding:

pgsr8r GillSans <pgsr8a.pfb

Do not read the font at all, or reencode it from font file —

pgsr8r GillSans !pgsr8a.pfb

Include font entirely and reencode:

pgsr8r GillSans <<pgsr8a.pfb 8r.enc

Partially include font and reencode:

pgsr8r GillSans <pgsr8a.pfb 8r.enc

Do not include font but extract parameters from font file and reencode — only works for font with Adobe Standard Encoding. The font flags says how this font looks like so AcroReader can generate similiar instance if the font resource is not available on the target system.

pgsr8r GillSans 32 pgsr8a.pfb 8r.enc

A TrueType font can be used in the same way as a Type 1 font:

verdana8r Verdana <verdana.ttf 8r.enc

A base font can also be reencoded:

phvr8r Helvetica 8r.enc

# **3.2** TrueType fonts

As mentioned above,  $pdfT_EX$  can work with TrueType fonts. Adding TrueType into map files is similar to Type 1 font. The only extra thing to do with TrueType is to create TFM. There is a program ttf2afm in  $pdfT_EX$  distribution which can be used to extract AFM from TrueType fonts. Usage is simple:

```
ttf2afm <ttf> [<encoding>]
```

ttf is the TrueType font file, the optimal *encoding* specifies the encoding, which is the same as encoding vector used in map files for pdfT<sub>E</sub>X and dvips. If the encoding is not given, all the glyphs of the AFM output will be mapped to /.notdef. ttf2afm writes the output AFM to standard output. The rest is easy, as we have AFM already. If we need to know which glyphs are available in the font, we can run ttf2afm without encoding to get all glyph names.

# 4 New primitives

There follows a short description of new primitives added by  $pdfT_{E}X$ . One way to learn more about how to use these primitives is to have a look at the file example.tex in the  $pdfT_{E}X$  distribution.

## 4.1 Document setup

#### $\pdfoutput = n$

Integer parameter specifying whether the output format should be DVI or PDF. Positive value means PDF output, otherwise DVI output. This parameter cannot be specified *after* shipping out the first page. In other words, this parameter must be set before pdfTEX ships out the first page if we want PDF output. This is the only one parameter that must be set to produce PDF output. All others are optional.

#### $\pdfcompresslevel = n$

Integer parameter specifying the level of text compression via zlib. Zero means no compression, 1 means fastest, 9 means best, 2..8 means something in between. A value out of this range will be adjusted to the nearest meaningfull value.

#### $\verb+pdfpagewidth=dimen$

#### \pdfpageheight = dimen

Dimension parameters specifying the page width and page height of PDF output. If not given then the page dimensions will be calculated as mentioned above.

#### \pdfpagesattr{*text*}

Token list parameter specifying optional attributes common for all pages of PDF output file. These attributes can be MediaBox (rectangle specifying the natural size of the page), CropBox (rectangle specifying the region of the page being displayed and printed), Rotate (number of degrees the page should be rotated clockwise when it is displayed or printed; must be 0 or a multiple of 90).

## \pdfpageattr{*text*}

this is similiar to \pdfpageattr, but it takes priority to the former one. It can be used to overwrite any attributes given by \pdfpagesattr for individual pages.

## 4.2 The document info and catalog

#### \pdfinfo{*info* keys}

This allows the user to add information to the document info section; if this is provided, it can be seen in Acrobat Reader with the menu option Document Information, General. The *info keys* parameter is a set of data pairs, a key and a value. The key names are preceded by a /, and the values are in parentheses; all keys are optional. The possible keys are /Author, /CreationDate (defaults to current date), /ModDate, /Creator (defaults to TeX), /Producer (defaults to pdfTeX), /Title, /Subject, and /Keywords.

/CreationDate and /ModDate are expressed in the form D:YYYYMMDDhhmmss), where YYYY is the year, MM is the month, DD is the day, hh is the hour, mm is the minutes, and ss is the seconds.

Multiple apperances of \pdfinfo will be concatenated to the only one. If a key is given more than once, then the first appearance will take priority. An example of use of \pdfinfo may look like:

```
\pdfinfo{
    /Title (example.pdf)
    /Creator (TeX)
    /Producer (pdfTeX)
    /Author (Tom and Jerry)
    /CreationDate (D:19980212201000)
    /ModDate (D:19980212201000)
    /Subject (Example)
    /Keywords (pdfTeX)
}
```

 $\column definition goto (num num - name{name}) appearance$ 

Similar to the document info section is the document catalog, where the available keys are /URI, which provides the base URL of the document, and /PageMode determines how Acrobat displays the document on startup. The possibilities for the latter are:

/UseNone	Open document with neither outline nor thumbnails
	visible.
/UseOutlines	Open document with outline visible.
/UseThumbs	Open document with thumbnails visible.
/FullScreen	Open document in full-screen mode. In full-screen mode,
	there is no menu bar, window controls, nor any other
	window present.

The default is /UseNone.

The *openaction* is the action provided when opening the document and is specified in the same way as for internal links (see below, section 4.6), e.g. goto page 3 {/Fit}.

# 4.3 Graphics inclusion

\pdfimage width width height height depth depth filename

Insert a bitmap image in PNG format, optionally changing width, height, depth or any combination of them. If all of them are given, the image will be scaled to fit the specified dimensions. If some of them (but not all) are given, the rest will be set to a value corresponding to the remaining ones so as to make the image size to yield the same proportion of width: (height + depth) as the natural image size, where depth is treated as zero. If non of them is given then the image will take the natural size of it. An image inserted at natural size often has resolution 72 DPI in output file, but some images may contain data specifying image resolution, and in such a case the image will be scaled to the intended resolution. The filename of the image must appear after the optional dimension parameters. The dimension of the image can be accessed by enclosing the **\pdfimage** command to a box and checking the dimensions of the box.

## 4.4 XObject Forms

 $\verb+pdfform $num$$ 

Write out the T<sub>E</sub>X box num as a XObject Form to the PDF file.

## $\pdflastform$

Returns the object number of the last XObject Form written to the PDF file

#### \pdfrefform \name

Put in a reference to the XObject Form called \name.

These macros support a feature called "object reuse" in pdfT<sub>E</sub>X. The idea is to create a Form object in PDF. The content of the XObject Form object corresponds to the content of a T<sub>E</sub>X box, which can also contain pictures and references to other XObject Form objects as well. After that the XObject Form can be used by simply referring to its object number. This feature can be useful for large document with a lot of similiar elements, as it can reduce the duplication of identical objects.

#### 4.5 Annotations

\pdfannot width height height depth {text}

Attach an annotation at the current point in the text. The text is inserted as raw PDF code to the contents of annotation.

#### \pdflastannot

Returns the object number of last annotation created by \pdfannot. These two primitives allow user to create any annotation that cannot be created by \pdfannotlink (see below).

## 4.6 Destinations and links

 $\verb|pdfdest \langle \textit{num num} - \textit{name}{name} \rangle appearance|$ 

Establish a destination for links and bookmark outlines; the link must be identified by either a number or a symbolic name, and the way Acrobat is to display the page must be specified; *appearance* must be one of

fit	fit whole page in window
fith	fit whole width of page
fitv	fit whole height of page
fitb	fit whole 'Bounding Box' page
fitbh	fit whole width of 'Bounding Box' of page
fitbv	fit whole height of 'Bounding Box; of page
xyz	keep current zoom factor

xyz can optionally be followed by  $zoom \ factor$  to provide a fixed zoom-in. The *factor* is like T<sub>E</sub>X magnification, ie 1000 is the 'normal' page view.

#### \pdfannotlink height height depth depth attr{attr} action

Start a hypertext link; if the optional dimensions are not specified, they will be calculated from the box containing the link. The *attributes* (explained in great detail in section 6.6 of the PDF manual) determine the appearance of the link. Typically, this is used to specify the color and thickness of any border around the link. Thus /C [0.9 0 0] /Border [0 0 2] specifies a color (in RGB) of dark red, and a border thickness of 2 points.

The *action* can do many things; some possibilities are

page $n$ goto num $n$	Jump to page $n$
goto name { <i>refname</i> } goto file { <i>filename</i> }	Jump to a point established as <i>name</i> with \pdfdest Open a local file; this can be used <i>with</i> a <i>name</i> or <i>num</i> specification, to point to a specific location on the file. Thus goto file{foo.pdf} name{intro}
thread num $\{n\}$	
thread name { <i>refname</i> } user { <i>spec</i> }	Jump to thread identified by <i>n</i> or <i>refname</i> Perform user-specified action. Section 6.9 of the PDF manual explains the possibilities. A typical use of this is to specify a URL, e.g. /S /URI /URI (http://www.tug.org/).

#### \pdfendlink

Ends link; all text between \pdfannotlink and \pdfendlink will be treated as part of this link. pdfT<sub>E</sub>X may break the result across lines (or pages), in which case it will make several links with the same content.

# 4.7 Bookmarks

\pdfoutline action count count {text}

Create a outline (or bookmark) entry. The first parameter specificies the action to be taken, and is the same as that allowed for \pdfannotlink. The *count* specifies the number of direct subentries under this entry, 0 if this entry has no subentries (in this case it may be omitted). If the number is negative, then all subentries will be closed and the absolute value of this number specifies the number of subentries. The *text* is what will be shown in the outline window (note that this is limited to characters in the PDFEncoding vector).

# 4.8 Article threads

## \pdfthread num num name{name}

Start an article thread; the corresponding  $\delta delta de$ 

#### $\pdfendthread$

Finish the current thread.

 $\pdfthreadhoffset = dimen$ 

 $\pdfthreadvoffset = dimen$ 

Specify thread margins.

#### 4.9 Miscellaneous

#### \pdfliteral{pdf text}

Like  $\special$  in normal  $T_EX$ , this command inserts raw PDF code into the output. This allows support of color, and text transformation.

#### \pdfobj stream {text}

Similar to \pdfliteral, but the text is inserted as contents of an object. If the optional keyword *stream* is given then the contents will be inserted as a stream.

\pdflastobj

Returns the object number of the last object created by \pdfobj. These primitives provide a mechanism allowing inserting a user-defined object to PDF output.

#### \pdfversion

Returns the version of pdfT<sub>E</sub>X multiple by 100, e.g. for version 0.12x it returns 12.

#### \pdfrevision

Returns the revision of  $pdfT_EX$ , e.g. for version 0.12x it returns x.

# 5 Graphics and color

Probably the biggest single usage problem with pdfT<sub>E</sub>X at the present time is the inclusion of graphics. The program only directly supports graphic inclusion in one bitmap format, PNG (Portable Network Graphics).

Two commonly-used techniques are not available — the inclusion of Encapsulated PostScript figures, and the inclusion of raw PostScript commands (the techique utilized by the pstricks package). Although PDF is a direct descendant of PostScript, it lacks any programming language commands, and cannot deal with arbitrary PostScript. There are two ways to proceed with existing EPS files: firstly, convert them to PNG (using programs like Image Magick, Image Alchemy, or Ghostscript); or secondly, try converting them to simple PDF. If the picture has no special fonts, the chances are quite good that Ghostscript's pdf writer will produce a file containing a single PDF object, which can be included using \pdfliteral commands (this is managed by the standard LATEX graphics package).

Other alternatives for graphics in pdfTEX are:

- 1. LATEX picture mode: since this is implemented simply in terms of font characters, it works in exactly the same way as usual;
- 2. Xy-pic: If the PostScript backend is not requested, Xy-pic uses its own Type 1 fonts, and needs no special attention;
- 3. tpic: The 'tpic' \special commands (used in some macro packages) can be redefined to produce literal PDF, using macros by Hans Hagen;
- 4. MetaPost: although the output of MetaPost is PostScript, it is in a highly simplified form, and a MetaPost to PDF conversion (written by Hans Hagen and Tanmoy Bhattacharya) is implemented as a set of macros which read MetaPost output and support all of its features;

5. It is possible to insert a "pure" PDF file (PDF that has only one page without fonts, bitmaps or other resources) using a macro package that reads the external PDF file line by line.

The two latter macro packages are part of CONT<sub>E</sub>XT (supp-pdf.tex and supp-mis.tex), but also work with LAT<sub>E</sub>X and are distributed separately.

For new work, the MetaPost route is highly recommended. For the future, Adobe have announced that they will define a specification for 'encapsulated PDF', and this should solve some of the present difficulties.

# 6 Macro packages supporting pdfT<sub>E</sub>X

- For LATEX users, Sebastian Rahtz' hyperref package has substantial support for pdfTEX, and provides access to most of its features. In the simplest case, the user merely needs to load hyperref with a 'pdftex' option, and all cross-references will be converted to PDF hypertext links. PDF output is automatically selected, text compression turned on, and the page size is set up correctly. Bookmarks are created to match the table of contents.
- The standard IATEX graphics and color packages have pdftex options, which allow use of normal color, text rotation, and graphics inclusion commands. Only PNG and MetaPost files can be included.
- The ConT<sub>E</sub>XT macro package by Hans Hagen (mailto:pragma@pi.net) has very full support for pdfT<sub>E</sub>X in its generalized hypertext features.
- Hypertexted PDF from texinfo documents can be created with pdftexinfo.tex, which is a slight modification of the standard texinfo macros. This is part of the pdfTEX distribution.
- A similiar modification of the webmac, called pdfwebmac.tex, allows production of hypertexted PDF versions of program written in WEB. This is part of the pdfT<sub>F</sub>X distribution.

Some nice samples of  $pdfT_EX$  output can be found on the TUG Web server, at http://www.tug.org/applications/pdftex/.